

---

# **VHH Plugin Package: Shot Boundary Detection (vhh\_sbd)**

***Release 1.0.0***

**Daniel Helm**

**Jun 08, 2020**

# CONTENTS

<b>1</b>	<b>Setup instructions</b>	<b>2</b>
<b>2</b>	<b>Parameter Description</b>	<b>3</b>
<b>3</b>	<b>API Description</b>	<b>4</b>
3.1	Configuration class . . . . .	4
3.2	CandidateSelection class . . . . .	4
3.3	Evaluation class . . . . .	5
3.4	PreProcessing class . . . . .	6
3.5	SBD class . . . . .	7
3.6	Shot class . . . . .	8
3.7	Video class . . . . .	9
3.8	Utils module . . . . .	9
<b>4</b>	<b>Indices and tables</b>	<b>10</b>
4.1	References . . . . .	10
	<b>Python Module Index</b>	<b>11</b>
	<b>Index</b>	<b>12</b>

The following list give an overview of the folder structure of this python repository:

*name of repository:* vhh\_sbd

- **ApiSphinxDocumentation/:** includes all files to generate the documentation as well as the created documentations (html, pdf)
- **config/:** this folder includes the required configuration file
- **sbd/:** this folder represents the shot-type-classification module and builds the main part of this repository
- **Demo/:** this folder includes a demo script to demonstrate how the package have to be used in customized applications
- **Develop/:** includes scripts to evaluate the implemented approach as well as several helper scripts used during development stage. Furthermore, a script is included to create the package documentation (pdf, html).
- **README.md:** this file gives a brief description of this repository (e.g. link to this documentation)
- **requirements.txt:** this file holds all python lib dependencies and is needed to install the package in your own virtual environment
- **setup.py:** this script is needed to install the sbd package in your own virtual environment

## SETUP INSTRUCTIONS

This package includes a `setup.py` script and a `requirements.txt` file which are needed to install this package for custom applications. The following instructions have to be done to use this library in your own application:

Requirements:

- Ubuntu 18.04 LTS
- CUDA 10.1 + cuDNN
- python version 3.6.x

Create a virtual environment:

- create a folder to a specified path (e.g. `/xxx/vhh_sbd/`)
- `python3 -m venv /xxx/vhh_sbd/`

Activate the environment:

- `source /xxx/vhh_sbd/bin/activate`

Checkout `vhh_sbd` repository to a specified folder:

- `git clone https://github.com/dahe-cvl/vhh\_sbd`

Install the `sbd` package and all dependencies:

- change to the root directory of the repository (includes `setup.py`)
- `python setup.py install`

---

**Note:** You can check the success of the installation by using the command `pip list`. This command should give you a list with all installed python packages and it should include `vhh_sbd`

---

---

**Note:** Currently there is an issue in the `setup.py` script. Therefore the pytorch libraries have to be installed manually by running the following command: `pip install torch==1.5.0+cu101 torchvision==0.6.0+cu101 -f https://download.pytorch.org/whl/torch\_stable.html`

---

## PARAMETER DESCRIPTION

**DEBUG\_FLAG** This parameter is used to activate or deactivate the debug mode.

**RESIZE\_DIM** This flag is used to specify the resize dimension. (only usable if **DOWNSCALE\_FLAG** is active).

**CONVERT2GRAY** This flag is used to convert a input frame into a grayscale frame (0... deactivate, 1... activate).

**CROP** This flag is used to center crop a input frame (0... deactivate, 1... activate).

**DOWNSCALE** This flag is used to scale a input frame into the specified dimension (0... deactivate, 1... activate).

**HISTOGRAM\_EQU** This parameter is used to specify a valid pre-processing method (clahe" or "classic" or "none).

**CANDIDATE\_SELECTION** This flag is used to enable or disable the candidate selection mode.

**SAVE\_RAW\_RESULTS** This parameter is used to save raw results (e.g. debug visualizations).

**PATH\_RAW\_RESULTS** This parameter is used to specify the path for saving the raw results.

**PREFIX\_RAW\_RESULTS** This parameter is used to specify the prefix for the results file.

**POSTFIX\_RAW\_RESULTS** This parameter is used to specify the postfix for the results file.

**SAVE\_FINAL\_RESULTS** This parameter is used to save final results (e.g. csv list).

**PATH\_FINAL\_RESULTS** This parameter is used to specify the path for saving the final results.

**PREFIX\_FINAL\_RESULTS** This parameter is used to specify the prefix for the results file.

**POSTFIX\_FINAL\_RESULTS** This parameter is used to specify the postfix for the results file.

**PATH\_VIDEOS** This parameter is used to specify the path to the videos.

**THRESHOLD\_MODE** This parameter is used to specify the threshold mode (adaptive OR fixed).

**THRESHOLD** This parameter is used to specify the threshold (only in fixed threshold mode - [0-1]).

**ALPHA** This parameter is used to specify the adaptive threshold.

**WINDOW\_SIZE** This parameter is used to specify the window size (frames history window - only for adaptive mode).

**BACKBONE\_CNN** This parameter is used to specify the backbone cnn model ( vgg16 OR squeezeNet).

**SIMILARITY\_METRIC** This parameter is used to specify the similarity metric (cosine OR euclidean).

**PATH\_PRETRAINED\_MODEL** This parameter is used to specify the path to the pre-trained model.

**SAVE\_EVAL\_RESULTS** This parameter is used to save evaluation results (e.g. visualizations, ... ).

**PATH\_RAW\_RESULTS** This parameter is used the raw results path.

**PATH\_EVAL\_RESULTS** This parameter is used to specify the path to store the evaluation results path.

**PATH\_GT\_ANNOTATIONS** This parameter is used to groundtruth annotations used for evaluation.

## API DESCRIPTION

This section gives an overview of all classes and modules in *sb*d as well as an code description.

### 3.1 Configuration class

**class** `sb`d.Configuration.Configuration(*config\_file: str*)

Bases: `object`

This class is needed to read the configuration parameters specified in the configuration.yaml file. The instance of the class is holding all parameters during runtime.

---

**Note:** e.g. `./config/config_vhh_test.yaml`

the yaml file is separated in multiple sections `config['Development']` `config['PreProcessing']` `config['SbdCore']` `config['Evaluation']`

whereas each section should hold related and meaningful parameters.

---

**loadConfig()**

Method to load configurables from the specified configuration file

### 3.2 CandidateSelection class

**class** `sb`d.DeepSBD.CandidateSelection(*config\_instance: sb*d.Configuration.Configuration)

Bases: `object`

This class is used for sbd candidate selection. It detects frames ranges of about 16 frames which includes an abrupt cut. The loaded model is pre-trained on the deepsbd dataset.

**run**(*video\_path*)

This method is used to run the candidate selection process.

**Parameters** `video_path` – This parameter must hold a valid path to a video file.

**Returns** This method returns a numpy array with a list of all detected frames ranges.

### 3.3 Evaluation class

**class** sbd.Evaluation.Evaluation(*config\_file: str*)

Bases: object

This class is used to evaluate the implemented algorithm.

**calculateEvaluationMetrics** ()

This method is used to calculate the evaluation metrics.

**Returns** This methods returns a numpy array including a list of the calculated metrics (precision, recall, ...).

**calculateMetrics** (*tp\_cnt, fp\_cnt, tn\_cnt, fn\_cnt*)

This method is used to calculate the evaluation metrics precision, recall and f1score.

**Parameters**

- **tp\_cnt** – This parameter must hold a valid integer representing the tp counter.
- **fp\_cnt** – This parameter must hold a valid integer representing the fp counter.
- **tn\_cnt** – This parameter must hold a valid integer representing the tn counter.
- **fn\_cnt** – This parameter must hold a valid integer representing the fn counter.

**Returns** This method returns the scores for precision, recall, accuracy, f1\_score, tp\_rate and fp\_rate.

**calculateSimilarityMetric** (*results\_np: numpy.ndarray, threshold=4.5*)

This method is used to calculate the similarity metrics based on the pre-calculated raw results.

**Parameters**

- **results\_np** – This parameter must hold a valid numpy array.
- **threshold** – This parameter holds a threshold. (default: 4.5)

**Returns** This method returns a numpy array including the final shot boundaries.

**evaluation** (*result\_np, vid\_name*)

This method is needed to evaluate the gathered results for a specified video.

**Parameters**

- **result\_np** – This parameter must hold a valid numpy array.
- **vid\_name** – This parameter represents a video name.

**Returns** This method returns the calculated TP, TN, FP and FN counters.

**export2CSV** (*data\_np: numpy.ndarray, header: str, filename: str, path: str*)

This method is used to export the gathered results to a csv file.

**Parameters**

- **data\_np** – This parameter holds a valid numpy array.
- **header** – This parameter holds a csv header line (first line in the file - semicolon separated).
- **filename** – This parameter must hold a valid file name.
- **path** – This parameter must hold a valid file path.

**exportMovieResultsToCSV** (*fName, res\_np*)

This method is used to export video results to csv file.

**Parameters**

- **filepath** – This parameter must hold a valid file\_path.
- **res\_np** – This parameter must hold a valid numpy array containing the final results.

**loadRawResultsFromCsv** (*filepath*)

This method is used to load raw results from csv file.

**Parameters** **filepath** – This parameter must hold a valid file\_path.

**Returns** This method returns a numpy array containing the raw\_results.

**loadRawResultsFromNumpy** (*filepath*)

This method is used to load raw results from numpy array.

**Parameters** **filepath** – This parameter must hold a valid file\_path.

**Returns** This method returns a numpy array containing the raw\_results.

**loadResultsFromCSV** (*filepath*)

This method is used to load final results from csv file.

**Parameters** **filepath** – This parameter must hold a valid file\_path.

**Returns** This method returns a numpy array containing the final results.

**plotPRCurve** (*results\_np*)

This method is needed to create and plot the precision\_recall curve.

**Parameters** **results\_np** – This parameter must hold a valid numpy array including the precision and recall scores.

**plotROCCurve** (*results\_np*)

This method is needed to create and plot the roc curve.

**Parameters** **results\_np** – This parameter must hold a valid numpy array including the precision and recall scores.

**run** ()

This method is needed to run the evaluation process.

## 3.4 PreProcessing class

**class** sbd.PreProcessing.PreProcessing (*config\_instance: sbd.Configuration.Configuration*)

Bases: object

This class is used to pre-process frames.

**applyTransformOnImg** (*image: numpy.ndarray*) → numpy.ndarray

This method is used to apply the configured pre-processing methods on a numpy frame.

**Parameters** **image** – This parameter must hold a valid numpy image (WxHxC).

**Returns** This methods returns the preprocessed numpy image.

**applyTransformOnImgSeq** (*img\_seq: numpy.ndarray*) → numpy.ndarray

**claHE** (*img: numpy.ndarray*)

This method is used to calculate the Contrast Limited Adaptive Histogram Equalization.

**Parameters** **img** – This parameter must hold a valid numpy image.

**Returns** This method returns the pre-processed image.



**classicHE** (*img: numpy.ndarray*)

This method is used to calculate the classic histogram equalization.

**Parameters** **img** – This parameter must hold a valid numpy image.

**Returns** This method returns the pre-processed image.

**convertRGB2Gray** (*img: numpy.ndarray*)

This method is used to convert a RGB numpy image to a grayscale image.

**Parameters** **img** – This parameter must hold a valid numpy image.

**Returns** This method returns a grayscale image (WxHx1).

**crop** (*img: numpy.ndarray, dim: tuple*)

This method is used to crop a specified region of interest from a given image.

**Parameters**

- **img** – This parameter must hold a valid numpy image.
- **dim** – This parameter must hold a valid tuple including the crop dimensions.

**Returns** This method returns the cropped image.

**resize** (*img: numpy.ndarray, dim: tuple*)

This method is used to resize a image.

**Parameters**

- **img** – This parameter must hold a valid numpy image.
- **dim** – This parameter must hold a valid tuple including the resize dimensions.

**Returns** This method returns the resized image.

## 3.5 SBD class

**class** sbd.SBD.SBD (*config\_file: str*)

Bases: object

Main class of shot boundary detection (sbd) package.

**calculateDistance** (*x, y*)

This method is used to calculate the distance between 2 feature vectors.

**Parameters**

- **x** – This parameter represents a feature vector (one-dimensional)
- **y** – This parameter represents a feature vector (one-dimensional)

**Returns** This method returns the similarity score of a specified distance metric.

**convertShotBoundaries2Shots** (*shot\_boundaries\_np: numpy.ndarray*)

This method converts a list with detected shot boundaries to the final shots.

**Parameters** **shot\_boundaries\_np** – This parameter must hold a numpy array with all detected shot boundaries.

**Returns** This method returns a numpy list with the final shots.

**exportFinalResultsToCsv** (*shot\_l: list, name: str*)

This method is used to export the final results to a csv file (semicolon seperated). :param shot\_l: This parameter must hold a valid array list including the final results list. :param name: This parameter represents the name of the csv list.

**exportRawResultsAsCsv\_New** (*results\_np: numpy.ndarray*)

This method is used to export the raw results to a csv file.

**Parameters** **results\_np** – This parameter must hold a valid numpy list including the raw results.

**exportRawResultsAsNumpy** (*results\_np: numpy.ndarray*)

This method is used to export the raw results to a numpy file.

**Parameters** **results\_np** – This parameter must hold a valid numpy list including the raw results.

**runOnFolder** ()

This method is used to run sbd on all video files included in a specified folder.

**Returns** This method returns a numpy list of all detected shots in all videos.

**runOnSingleVideo** (*video\_filename, max\_recall\_id=- 1*)

Method to run sbd on specified video.

**Parameters**

- **video\_filename** – This parameter must hold a valid video file path.
- **max\_recall\_id** – [required] integer value holding unique video id from VHH MMSI system

**runWithCandidateSelection** (*candidates\_np*)

This method is used to run sbd with candidate selection mode.

**Parameters** **candidates\_np** – This parameter must hold a valid numpy list including all pre-selected candidates.

**Returns** This method returns a numpy list with all detected shots in a video.

**runWithoutCandidateSelection** (*src\_path, vid\_name*)

This method is used to run sbd without candidate selection mode.

**Parameters**

- **src\_path** – This parameter must hold a valid path to the video file.
- **vid\_name** – This parameter must hold a valid videofile name.

**Returns** This method returns a numpy list with all detected shots in a video.

## 3.6 Shot class

**class** `sbd.Shot.Shot` (*sid, movie\_name, start\_pos, end\_pos*)

Bases: `object`

This class represents on shot and contains shot properties such as start/end frame index of a shot, shot-id and video\_name.

**convert2String** ()

This method is used to convert all properties of a shot into a semicolon-separated string. :return:

**printShotInfo()**

This method is used to print all properties of a shot.

## 3.7 Video class

**class** sbd.Video.Video

Bases: object

This class represents on video and contains properties such as dimensions, length, format, video name ...

**getFrame** (*frame\_id: int*) → numpy.ndarray

This method is used to return one frame specified with a given frame index.

**Parameters** **frame\_id** – This parameter must hold a valid integer frame index.

**Returns** This method returns a numpy frame with a specified index (position).

**load** (*vidFile: str*)

This method is used to load a video of a specified storage.

**Parameters** **vidFile** – This parameter must hold a valid video file path.

**printVIDInfo()**

This method is used to print all video properties.

## 3.8 Utils module

**class** sbd.utils.STDOUT\_TYPE

Bases: object

This class represents message types.

**ERROR = 2**

**INFO = 1**

**sbd.utils.getCommandLineParams()**

This function is used to read commandline parameters (e.g. just used in development stage) :return: list of parameters.

**sbd.utils.printCustom** (*msg: str, type: int*)

This function represents a customized print function (error/info msg). :param msg: Message to print. :param type: Type of message (info or error).

## INDICES AND TABLES

- `genindex`
- `modindex`
- `search`

### 4.1 References

## PYTHON MODULE INDEX

### S

`sbd.utils`, 9

## A

applyTransformOnImg() (*sbd.PreProcessing.PreProcessing method*), 6  
 applyTransformOnImgSeq() (*sbd.PreProcessing.PreProcessing method*), 6

## C

calculateDistance() (*sbd.SBD.SBD method*), 7  
 calculateEvaluationMetrics() (*sbd.Evaluation.Evaluation method*), 5  
 calculateMetrics() (*sbd.Evaluation.Evaluation method*), 5  
 calculateSimilarityMetric() (*sbd.Evaluation.Evaluation method*), 5  
 CandidateSelection (*class in sbd.DeepSBD*), 4  
 claHE() (*sbd.PreProcessing.PreProcessing method*), 6  
 classicHE() (*sbd.PreProcessing.PreProcessing method*), 6  
 Configuration (*class in sbd.Configuration*), 4  
 convert2String() (*sbd.Shot.Shot method*), 8  
 convertRGB2Gray() (*sbd.PreProcessing.PreProcessing method*), 7  
 convertShotBoundaries2Shots() (*sbd.SBD.SBD method*), 7  
 crop() (*sbd.PreProcessing.PreProcessing method*), 7

## E

ERROR (*sbd.utils.STDOUT\_TYPE attribute*), 9  
 Evaluation (*class in sbd.Evaluation*), 5  
 evaluation() (*sbd.Evaluation.Evaluation method*), 5  
 export2CSV() (*sbd.Evaluation.Evaluation method*), 5  
 exportFinalResultsToCsv() (*sbd.SBD.SBD method*), 7  
 exportMovieResultsToCSV() (*sbd.Evaluation.Evaluation method*), 5  
 exportRawResultsAsCsv\_New() (*sbd.SBD.SBD method*), 8  
 exportRawResultsAsNumpy() (*sbd.SBD.SBD method*), 8

## G

getCommandLineParams() (*in module sbd.utils*), 9

getFrame() (*sbd.Video.Video method*), 9

## I

INFO (*sbd.utils.STDOUT\_TYPE attribute*), 9

## L

load() (*sbd.Video.Video method*), 9  
 loadConfig() (*sbd.Configuration.Configuration method*), 4  
 loadRawResultsFromCsv() (*sbd.Evaluation.Evaluation method*), 6  
 loadRawResultsFromNumpy() (*sbd.Evaluation.Evaluation method*), 6  
 loadResultsFromCSV() (*sbd.Evaluation.Evaluation method*), 6

## M

module  
     sbd.utils, 9

## P

plotPRCurve() (*sbd.Evaluation.Evaluation method*), 6  
 plotROCCurve() (*sbd.Evaluation.Evaluation method*), 6  
 PreProcessing (*class in sbd.PreProcessing*), 6  
 printCustom() (*in module sbd.utils*), 9  
 printShotInfo() (*sbd.Shot.Shot method*), 8  
 printVIDInfo() (*sbd.Video.Video method*), 9

## R

resize() (*sbd.PreProcessing.PreProcessing method*), 7  
 run() (*sbd.DeepSBD.CandidateSelection method*), 4  
 run() (*sbd.Evaluation.Evaluation method*), 6  
 runOnFolder() (*sbd.SBD.SBD method*), 8  
 runOnSingleVideo() (*sbd.SBD.SBD method*), 8  
 runWithCandidateSelection() (*sbd.SBD.SBD method*), 8  
 runWithoutCandidateSelection() (*sbd.SBD.SBD method*), 8

## S

SBD (*class in sbd.SBD*), [7](#)

sbd.utils

module, [9](#)

Shot (*class in sbd.Shot*), [8](#)

STDOUT\_TYPE (*class in sbd.utils*), [9](#)

## V

Video (*class in sbd.Video*), [9](#)